一、 服务端设置

1、电脑上安装 Radmin Server3.4 版本软件,点击开始菜单找到 Radmin Server3 菜单, 点击打开 Settings for Radmin Server进行设置;

2、点 '选项 '按钮, 弹出 "Radmin服务器选项", 可以设置端口 (默认为 4489)、暂停联机 模式, ip 过滤等, 设置完关闭即可(参数使用默认配置即可)。如下图所示:

- General - Miscellaneous - IP Filter - Language	Port Vse default p 4899	Tray icon Show in system tray 🕶
<ul> <li>Chat Options</li> <li>Appearance</li> <li>Additional</li> <li>Voice Chat Options</li> <li>Audio Devices</li> </ul>	Incoming connection d Ask user permissi Auto deny after t Auto allow after Timeout 10 sec Logging All errors • Use Event Log Vse logfil C:\Windows\SysWOW64	i alog on imeon timeo *

3、在"Radmin服务器设置"窗口点"Permissions"按钮,弹出"服务器安全模式" 窗口。如下图所示:

	Radmin Server Security Mod	le 🔀	
Ru-Board	Set user/password verific	cation mode	Options
	Radmin security	Permissions	Permissions .
	🔘 Windows NT securit;	Permissions	Help
Company in			herp
	OK	Cancel	Advanced

4、在以上窗口选择 Radmin安全性,右边点" Permissions 按钮,弹出的界面点击 Add User 用来添加登陆服务器的用户名和密码,我这里用的是用户名: root,密码: 123456。OK确认之后勾选 All access 选型给予该用户所有操作权限,如下图所示:

Rada Settings for Ra Radmi Lice Ru-E	nin Vsers			E3 rtup mode
Settings for Ra Radmi: Lice Ru-E				E3 rtup mode ptions
Ru-I		611.17		E
Ri	Add New Radmin Us	er		missions
Comp. R Web R	User name Password	rt		Help dvanced
All components rights reserve Copyright © 19 R C	Confirm password	Cancel	]	Exit
Aŭ Se Sh	dio Chat (A) nd Message (M) utdown (S)		-	

	Badada Massa			
	Kadmin Users			
	root			
ettings for Ra				23
Badmi				
۳	£		rtup mode	B
Lie			ptions	]
Ru-I	Add	User Remov	ve User	84985 
			missions	
	Rights	Allow		
	All Access	Allow	- Help	
Comp	Rights All Access Remote Screen Control (R)	Allow	Help	
Comp Web	Rights All Access Remote Screen Control (R) Remote Screen View (V)	Allow V V	Melp dvanced.	
Comp Wab	Rights All Access Remote Screen Control (R) Remote Screen View (V) Telnet (T)	Allow V V V	Melp dvanced .	
Comp Wab 11 components 1 ghts reserve	Rights All Access Remote Screen Control (R) Remote Screen View (V) Telnet (T) File Transfer (F)		<pre>Melp dvanced . Exit</pre>	
Comp Web ights reserve opyright © 15	Rights All Access Remote Screen Control (R) Remote Screen View (V) Telnet (T) File Transfer (F) Redirect (D)		Melp dvanced .	
Comp Web Il components ights reserve opyright © 19	Rights All Access Remote Screen Control (R) Remote Screen View (V) Telnet (T) File Transfer (F) Redirect (D) Chat (C)		Melp dvanced .	
Comp Wab ll components ights reserve opyright © 19	Rights All Access Remote Screen Control (R) Remote Screen View (V) Telnet (T) File Transfer (F) Redirect (D) Chat (C) Audio Chat (A)		Melp dvanced . Exit	
Comp Web ights reserve opyright © 19	Rights All Access Remote Screen Control (R) Remote Screen View (V) Telnet (T) File Transfer (F) Redirect (D) Chat (C) Audio Chat (A) Send Message (M)		Melp dvanced. Exit	

- 5、至此服务器设置基本设置完成,确认退出然后再重新启动一下 Radmin服务即可。
- 二、 查看程序 (Radmin 控制端) 设置

1、运行"RadminViewer 3. Radmin.exe"点击左上角的 《 闪电按钮来连接到服务器, 选择联机模式,在 ip 地址或 dns 名称栏输入 ip 地址,我这里服务端的 ip 地址是 10.1.1.204,

联机选择完全控制,如下图所示:



2、设置完点确定,输入用户名和密码就可以连接到 Radmin服务器了。

